

Commands to Control the 1-DOF Laser Robot

Command	Shorthand	Parameter	Description
todeg	td	float (degrees)	Rotate to an absolute degree position.
bydeg	bd	float (degrees)	Rotate by a specified degree.
tostep	ts	int (steps)	Rotate to an absolute step position.
bystep	bs	int (steps)	Rotate by a specified number of steps.
tohole	th	int (hole number)	Rotate to an absolute hole position.
byhole	bh	int (hole number)	Rotate by a specified number of holes.
setdeg	sd	float (degrees)	Set the current position in degrees.
setstep	ss	int (steps)	Set the current position in steps.
settlr	st	int (microseconds)	Set the delay tolerance in microseconds.
setzero	sz	No parameter	Set the current position to zero degrees.
homezero	hz	No parameter	Home to the zero position.
tolimsw	tl	No parameter	Rotate to the limit switch.
laseron	ln	No parameter	Turn on the laser.
laserooff	lf	No parameter	Turn off the laser.
beam	bm	int (duration in ms)	Emit a laser beam for a specified duration.
withweight	ww	No parameter	Set the position of limit switch for use with weight.
noweight	nw	No parameter	Set the position of limit switch for use without weight.
printpos	pp	No parameter	Print the current position in steps and degrees.